

See also: [Uploads](#), [Uploads admin](#).

### [\\$EnableUpload](#)

The upload.php script is automatically included from stdconfig.php if the [\\$EnableUpload](#) variable is true in config.php. Note that

### [\\$UploadDir](#)

The directory where uploads are to be stored. Defaults to *uploads*/in the pmwiki directory, but can be set to any location on the s

### [\\$UploadUrlFmt](#)

The url of the directory given by [\\$UploadDir](#). By default, [\\$UploadUrlFmt](#) is derived from [\\$PubDirUrl](#) and [\\$UploadDir](#).  
[\\$IMapLinkFmt](#)['Attach:']

The format of the upload link displayed when an attachment is present. No default is set.

### [\\$LinkUploadCreateFmt](#)

The format of the upload link displayed when an attachment not present. Defaults to  
`<a class='createlinktext' href='\$LinkUpload'>\$LinkText</a>  
<a class='createlink' href='\$LinkUpload'> &Delta; </a>" );`

### [\\$UploadPrefixFmt](#)

Sets the prefix for uploaded files to allow attachments to be organized other than by groups. Defaults to '/\$Group' (uploads are  
`$UploadPrefixFmt = '/$Group/$Name'; # per-page attachments $UploadPrefixFmt = '';` #  
sitewide attachments

It is recommended to have the [\\$UploadPrefixFmt](#) variable defined in config.php, the same for all pages in the wiki, and not in

#### [\\$EnableDirectDownload](#)

When set to 1 (the default), links to attachments bypass PmWiki and come directly from the webserver. Setting [\\$EnableDirect](#)

#### [\\$EnableUploadGroupAuth](#)

Set [\\$EnableUploadGroupAuth](#) = 1; to authenticate downloads with the group password. This could be used together with [\\$](#)

#### [\\$EnableUploadVersions](#)

When set to 1 (default is 0), uploading a file to a location where a file of the same name already exists causes the old version to

#### [\\$EnableUploadOverwrite](#)

When set to 1 (the default), determines if overwriting previously uploaded files is allowed.

#### [\\$UploadNameChars](#)

The set of characters allowed in upload names. Defaults to "-\w. ", which means alphanumerics, hyphens, underscores, dots,

[\\$UploadNameChars](#) = "-\w. !=+"; # allow exclamations, equals, and plus

[\\$UploadNameChars](#) = "-\w. \x80-\xff"; # allow unicode

#### [\\$MakeUploadNamePatterns](#)

An array of regular expression replacements that is used to normalize the filename of an attached file. First, everything but [\\$Uplo](#)

#### [\\$UploadDirQuota](#)

Overall size limit for all uploads.

```
$UploadDirQuota = 100*1024;          # limit uploads to 100KiB
$UploadDirQuota = 1000*1024;         # limit uploads to 1000KiB
$UploadDirQuota = 1024*1024;        # limit uploads to 1MiB
$UploadDirQuota = 25*1024*1024;     # limit uploads to 25MiB
$UploadDirQuota = 2*1024*1024*1024; # limit uploads to 2GiB
```

### [\\$UploadPrefixQuota](#)

Overall size limit for one directory containing uploads. This directory is usually uploads/GroupName (one for every WikiGroup).

### [\\$UploadMaxSize](#)

Maximum size for uploading files, 50000 octets (bytes) by default.

### [\\$UploadExtSize](#)

Maximum size per extension, overriding the default in [\\$UploadMaxSize](#).

```
$UploadExtSize['zip'] = 2*1024*1024; # allow up to 2MiB for zip files
```

# Copyright: Petko - 04/09/2010